# J74 AuNetTools

A tool set for audio/MIDI/sync network communication in Ableton Live



## Introduction

AuNetTools is a set of devices for Ableton Live which enables real-time audio and MIDI communication between computers across a TCP/IP network. By using these devices it is possible to collaborate with other musicians across a network (for instance using several computers on a Local Area Network – LAN, on a wireless LAN environment), to process audio outside of Live on a separate computer or to monitor audio remotely.

The possibilities offered by the tool set include:

• Send audio *from Ableton Live on* a computer *to* another computer running also *Ableton Live*, allowing collaboration between Ableton Live users across the network.



• Send MIDI (and transport sync information) *from Ableton Live* on a computer *to* another computer running also *Ableton Live*, as a virtual MIDI cable across the network.



• Send audio from a computer input using the AuSend standalone application to another computer running Ableton Live: for instance a musician playing a guitar plugged to computer A can send audio to an another computer B running Ableton Live.



• Receive and monitor an Ableton Live audio session on a remote computer running the AuRcv standalone application. Note: the audio cannot be routed by the AuRcv standalone to another application on the same computer, only to the computer soundcard output.



• Send MIDI *from a computer using the standalone "send"* application *to* another computer running *Ableton Live*, as virtual MIDI input to Live.



• Send MIDI *from Ableton Live* on a computer *to* another computer running the "receive" standalone and through this to a MIDI interface or application (in this case using a computer internal MIDI bus, such as the IAC bus on a Mac or MIDI Yoke on Windows)



#### **IMPORTANT NOTES:**

- A Max for Live license is required to be able to use the AuNetTools devices.
- On Windows it is required to have Quick Time installed (free download from Apple.com).
- On Windows auto-configuration requires Java to be installed (free download from <u>www.java.com/en/download</u>). Manual configuration does not require Java.
- The devices operate at their best when used on a reliable network and in conditions of low network latency (20 ms or below). These conditions are normally met in a LAN environment. A Wi-Fi (WLAN) network may or may not satisfy this requirement and therefore give lesser results.
- In theory the tools may also be used across the Internet. Anyway be aware that long distances can
  easily add latencies of 50ms or more (>100ms if international distances are involved). This may
  make real-time collaboration unpleasant and decrease audio quality. Moreover, using the public
  Internet as transport, typically comes with some complications in getting the devices to work. In
  particular you will probably have to deal with the issues related to NAT (Network Address
  Translation), as applied by network elements across the path. These issues can be workarounded,
  but require you to add some complex customization to your network environment.

## **Table of Contents**

Introduction	1
The AuNetTools J74 devices	4
Quality, Latency and Network setup	5
Device setup and Examples	7

### The AuNetTools J74 devices

The following characterizes the devices included in this tool set:

- **"AuSend J74.amxd"**. This device sends incoming *audio to another system* on the network. The remote system could be running either another Ableton Live instance (with the companion "AuRcv J74.amxd" device) or to the standalone little application "AuRcv J74" program, which enables monitoring outside Live. This device is an audio effect device in Live.
  - In the case of Ableton to Ableton a simple form of collaborative jamming over the net is possible, with signals routed within the Live applications and between them across the net.
  - In the case Ableton to standalone "AuRcv J74" you have a simple way to perform audio monitoring across the network.
- **"AuRcv J74.amxd"**. Companion of the previously mentioned device, allows you to receive audio *from another system* in the network, a system running either another Ableton Live instance (with the companion "AuSend J74.amxd" device) or the standalone little application "AuSend J74" for sending incoming audio from the system OS. This device is an audio effect device in Live.
  - The first case is identical to the first case already reported in the topic above in the case of Ableton to Ableton network collaboration.
  - The second case allows you to have a network collaboration between a musician plugging audio to the OS/audio interface and working as a virtual input to the remote Ableton Live session.
- **"MIDISend J74.amxd"**. sends incoming *MIDI to another system* AND *Live transport information* on the network, system either running another Ableton Live instance and using the companion device "MIDIRcv J74.amxd" for receiving the MIDI signal or to the standalone little application "MIDIRcv J74" program, which enables routing of MIDI outside Live. This device is a MIDI effect device in Live.
- "MIDIRcv J74.amxd". Companion of the "MIDISend J74.amxd" device, it allows you to receive MIDI and *Live transport information from another system* in the network, a system running either another Ableton Live instance (with the companion "MIDISend J74.amxd" device) or running the standalone little application "MIDISend J74" program for sending MIDI directly from the system OS. This device is a MIDI effect device in Live.
- "AuSend J74" (standalone). The standalone application can be used as a remote audio plug for sending audio to an Ableton Live remote computer (running the "AuRcv J74.amxd" device). The standalone AuSend device will be limited *to the inputs available on your sound card*. Sending audio from an application through the standalone AuSend on the same computer is not possible (there is no way to route this in input to the AuSend standalone).
- **"AuRcv J74" (standalone)**. Standalone application which allows you to receive audio *from another system* in the network such as one running Ableton Live with the companion "AuSend J74.amxd" device. Output on the AuRcv standalone can only be routed to your soundcard output.
- **"MIDISend J74" (standalone)**. This standalone little application can be used to route incoming MIDI *to another system* on the network, running another Ableton Live instance (and using the companion device "MIDIRcv J74.amxd") or to the standalone little application "MIDIRcv J74" program.
- **"MIDIRcv J74" (standalone)**. Standalone little application able to receive MIDI *from another system* in the network, either sent by an Ableton Live instance (with the companion "MIDISend J74.amxd" device) or by the standalone little application "MIDISend J74".

## About Quality, Latency and Network setup

#### Audio Quality (compression of audio)

The devices sending/receiving audio use a form of compression to keep bandwidth usage limited and allow efficient transmission of the audio signal (incoming samples are grouped in a numeric buffer of a few bytes for transmission). Once on the receiving side the process is reverted, rebuilding the audio signal from the group of numbers received through the packets. In terms of audio quality / manipulation this process somehow resembles a MP3-like compression process, with quality varying depending on the network conditions (such as stability of the latency, which as we will see requires some buffering to work properly).

#### Network Latency and Latency Adaptation Buffer on the Receiver's end

Apart from specifying the actual network parameters for transmission (as the target <u>IP address</u> - to be specified on the sender side only - and the used <u>TCP port</u> - on both sender and receiver sides), an additional parameter can be configured on the Audio Receiver end to tune the device: the <u>Latency Adaptation buffer</u>.

This parameter influences the way the receiving side does "buffering": by holding the output for a little amount of time the receiver side can compensate latency fluctuations (jitter) in the transmission and avoid clicks and/or artifacts in audio reproduction. This buffer, though, will add as much additional latency as its configured buffer length (the parameter is expressed in ms).

As a generic guideline the Latency Adaptation parameter should be normally set to match at least the same value of the network latency involved and anyway to be set as the best compromise possible for your specific setup (e.g. capacity of the sender and receiver to process packets at constant pace). The Latency Adaptation buffer should *be long enough to avoid clicks and artifacts, but also be as low as possible to limit additional latency.* 

In ideal network conditions, as often matched by a LAN environment, the latency of the network will be small and practically constant. In this case even a latency estimate buffer as low as 5ms could do a good job. In most LAN conditions a value of 10-15ms should produce smooth, high quality reproduction.

Instead, when using the application through the Internet, you should expect much longer latencies and consequently higher levels of latency fluctuation. Therefore buffers may even need values as high as 100ms or more.

<u>Important</u>: Be aware that *some latency will always be present using these devices*.

In the case of <u>MIDI</u>, latency will be in general comparable to the network latency (if your network has 10ms of latency, so MIDI communication will have).

In the <u>Audio</u> case latency will be given by the *sum* of the network latency and of the Latency Adaptation buffer you configured (if your network has 5ms of latency and the Latency Adaptation buffer works fine at 10ms, the result will be a total Audio latency of 5+10 = 15ms).

<u>Note</u>: Best audio quality results are achieved at low latency (< 20ms), with negligible jitter (latency fluctuation) and with 100% reliability (no packet drops). A LAN environment based on wired Ethernet 100Mbps or higher UTP normally satisfies these conditions.

#### About Internet as transport and the effect of NAT (Network Address Translation)

AuNetTools is <u>not</u> optimized for Internet usage. Apart from the very high latency involved, you will practically always have to deal with Network Address Translation (NAT) issues. To explain what NAT is in detail goes far beyond the scope of this manual. Anyway some advices are collected in the next paragraphs.

<u>For who wants to know what NAT does</u>: In short the purpose of NAT is to hide the local IP addresses of you computer *behind* a public IP address, as assigned by your Internet provider and in use on the router which connects you to the Internet. This router, doing the NAT, will translate (dynamically) the source IP address in packets you generate with the public IP address of the router. In this way any web server which receives your data packets will see in the packet envelope (header) that this packet was generated by the router. The web server will then be able to route back the required answer using the public IP as destination of the response packets. These will arrive to your Internet router, which will translate the IP back to your local IP address reversing the NAT done in first place. So NAT is good if you go to the Internet for browsing or downloading (it protects your computer and allows many computer in the same LAN to share a single Internet connection) but blocks communication if initiated by the "outside" (public side of the NAT boundary). To make this long story a short one, NAT on the receiving side will hide the local address of the receiving computer from the sending one.

The negative side effects of NAT to the communication path required by the AuNetTools can be workarounded only by creating a static NAT opening (sometimes called static TCP/UDP port translation) on the receiving side. This could be done, in most cases, directly on the internet router facing the receiving computer. The configuration typically requires you (or the administrator of your network) to enter the NAT setup on the Internet router and specify that a given set of protocols and ports (for the audio application in the AuNetTools the defaults are protocol/port TCP/5001 for audio and UDP/6001 for MIDI) and add a "mapping" for these to a given computer local IP address.

Example:

- Let's say the receiving side computer has local IP 192.168.1.22
- The Internet router of the receiving side has public IP address is 123.34.56.67
- The protocol/port combination for sending audio is TCP/5001 (default on the audio send devices)
- The protocol/port combination for sending MIDI is UDP/6001 (default on the MIDI send devices)

The configuration you need involves:

- Set up the Internet router NAT table to have these mapping:
  - TCP port 5001 mapped to IP 192.168.1.22 (keeping the same protocol/port as TCP port 5001)
  - UDP port 6001 mapped to IP 192.168.1.22 (keeping the same protocol/port as UDP port 6001)
- Set up the sending devices / applications to use as target the public IP on the receiving side (123.34.56.67 in this example) with as protocols/ports the same as set on the receiver side and opened in the NAT table (TCP/5001 for audio devices, UDP/6001 for MIDI devices in this example).

#### OS permissions for network connectivity to the applications

You may be prompted by your Operative System (OS) to <u>allow</u> a device in the AuNetTools set the use of the network. Some OS, such as Windows Vista, ask you this as they apply a standard firewall to applications and require your explicit approval when the applications are launched. Moreover if you use a local firewall on your computer be sure the protocol/port combinations required (by default TCP port 5001 and UDP port 6001) are not blocked.

#### Just to know: unicast only, no multicast (streaming) possible

The applications in the AuNetTools set allow you only to communicate with a single receiver per sending device (so called unicast communication). Multicast audio streaming is not supported.

## **Device setup and Examples**

Let's see some examples and set up in practice.

#### Audio from Ableton Live ("AuSend J74.amxd") to Standalone ("AuRcv J74")

In this setup we will use a computer in the (LAN) network (System 2) as a monitor system for an audio track playing on an Ableton Live instance on another computer (System 1). The following applies:

- System 1 runs Ableton Live and has local IP address 192.168.1.41
- In the live set we will monitor audio track "Audio 1", sent out using the "AuSend J74.amxd" Max for Live device to remote IP address 192.168.1.5 (port being the default one, TCP port 5001).
- System 2 runs the standalone application "AuRcv J74", set to listen to TCP port 5001 (the default)
- Latency estimate on the receiver (used for buffering audio) is left to default value of 50ms



In the picture below the sender side with the "AuSend J74.amxd" device directly (as audio effect) on the track. The device is configured to have the IP of the target computer as 192.168.1.5 and the TCP is left to the 5001 default value. Once we see the "connected" box lighting up this means the connection is ready to be used (it signals the fact the other side, the "AuRcv J74" device, has received and accepted the TCP "socket" for the communication). If we activate the toggle in the upper part of the device [Closed/Opened], the actual data (audio) will start to flow (the toggle changes in this case to "Opened").



Note: In this setup the monitored track gets muted by the "AuSend J74.amxd" device (it has no local output). If you require local monitoring for this track, use Live built in I/O audio routing to have another audio track monitoring the audio locally.

Let's now look on what happens on the receiver side. First of all, on this second computer (System 2), when we opened the "AuRcv J74" application we got a pop-up from the operative system (Windows Vista) requiring us to explicitly allow the application for the use of the network:

S AuRcvd J74	Windows Security Alert		
File Edit Window Help           Latency Adaptation         50	Windows Firew	vall has blocked some features of this program	
TCP port 5001	Windows Firewall has blocked th unblock this program, it will be u risks of unblocking a program?	nis program from accepting incoming network connections. If you inblocked on all public networks that you connect to. What are the	
Not connected	Name:	MaxMSP	
	Publisher:	Cycling '74	
	Path:	D:\my projects\j74 audionettools\j74 audionettools - window:	
Audio Setup	Network location:	Public network	
0.0 dB		What are network locations?	
		Keep blocking Unblock	

Do not miss this step! Click on "Unblock" and the TCP/IP communication will be enabled (next time you should not be asked the same question). As this is the very first time we opened the application we also need to setup the audio settings. We do this by clicking on the "Audio Setup" button, which opens up a new pop-up window. We choose the audio interface and we activate audio by setting this "On". Ready to go!

S AuRcvd J74	S DSP Status
Latency Adaptation 50 TCP port 5001	Audio     On     DSP       Driver     ad_asio ASIO E-MU 0404.     \$       Clock Source     Internal     \$       Output Limiting     On     \$       Output Destination     \$     \$       Playthrough Input     \$     \$
0.0 dB	I/O Vector Size       352       \$ Sampling Rate         Signal Vector Size       32       \$ 44100       Hz         Scheduler in Overdrive       In Audio Interrupt       \$         CPU Utilization (%)       0.       •         CPU Limit (%)       0       Overload       \$         Signals Used       2       Function Calls       7
	Input Channels  Quiput Channels  Channel 1 1 Analo.  Channel 1 1 Analo.  Channel 2 2 Analo.  Channel 2 2 Analo.  UO Mappings

As soon as audio is played on System 1 audio track, the remote computer (System 2) will receive the audio on the "AuRcvd J74" standalone application.

#### Audio and MIDI between two Ableton Live sessions

In the next example we will see how we can set up communication of audio, MIDI and transport information simultaneously between two computers running separate Ableton Live sessions. We have:

- System 1 with a MIDI track sending MIDI to System 2
- System 2 set to receive this MIDI information on a track with a Drum Rack as instrument
- System 2 routing in live audio to a second (audio) track and sending this audio to System 1
- System 1 receiving this audio on a dedicated, second (audio) track



The first picture shows System 1 (a Windows computer) having a MIDI track ("1 MIDI OUT") with a MIDI clip playing and the "MIDISend J74.amxd" used to send, in real time, this MIDI information to System 2 (the remote IP host, 192.168.1.41). The protocol/port is left to the default UDP port 6001.

ຄ Un	titled* - Live 8					
File Edit Create View Options Help						
TAP	120.00	II 4 / 4 00	••• 245.1.1 🔹 🔳 ● OVR 🧮 1Bar 👳 🖉			
0						
	1 MIDI OUT	2 Audio IN				
0	Test					
č						
۹						
0						
0						
ä						
9						
	.44 🕐 4					
1	MIDI From	Audio From				
	All Ins 👳	Ext. In 👳				
	I All Channe⇒	II 1/2 ♥				
	Monitor	Monitor				
	MIDI To	Audio To				
	No Output 👳	Master 👳				
	1 S Ø Track Delay	2 8 • •				
	0.00 ms	0.00 ms				
-	94					
6	MIDISend J74	000				
	MIDISend J74     (a)     (b)       Opened       Remote IP host       192     168       192     168       1     UDP port       6001       Send_Live_API_OFF					

The next picture shows System 2 (a Mac computer) having an instrument track ("1 DrRack") hosting the "MIDIRcv j74.amxd" device which receives the MIDI from System 2. The device is left on its default settings (protocol/port combination UDP/6001, which matches the settings on System 1).



The received MIDI information is used to play a Drum-Rack ("Kit-808"), as it would be done by local MIDI input. The audio produced in this case is further processed by an "EQ Eight" equalizer on the track. The chain is therefore a normal MIDI->Instrument->AudioFX chain.

On the same computer System 2 an additional (audio) track, named "2 Audio OUT", is used to monitor the audio (through Live's I/O internal routing) as produced by the Drum-rack track. Using the "AuSend J74.amxd" device on this track audio is sent to System 1.

The "AuSend J74.amxd" device is set with target IP address 192.168.1.5 (System 1) and uses the default TCP port 5001. The next picture shows this audio track hosting the "AuSend J74.amxd" device.



On System 1 an audio track ("2 Audio IN") is used to receive the audio from System 2. On this track the "AuRcv J74.amxd" device is hosted for receiving the information from the network and outputs the audio signal further in the track. This is shown in the next picture.

Looking at this picture notice also the fact of having the <u>Latency Adaptation changed to 10ms</u>, which in this conditions (a stable and quick LAN environment) still produce a good audio quality result but at a quite tolerable (low) amount of total end-to-end latency.



As a final step let's what we need to do to add *transport and tempo synchronization* between the two Ableton Live livesets. We will have System 1 controlling System 2 in this case.

This is possible using the same "MIDISend J74.amxd" and "MIDIRcv j74.amxd" devices already in use. On the "MIDISend J74.amxd" device, as placed on track 1 of the Live set of System 1, notice the toggle at the bottom. Once activated (yellow) this toggle will show the "Send\_Live\_API\_ON" label: this signifies that any transport change done to the liveset on System 1 (including tempo settings) will be sent to System 2.

Let's see what we need to do to accept this control information on System 2.

On System 2 we need to acknowledge this setting using th controls on the "MIDIRcv j74.amxd" device.



We have two options:

- The first toggle showing [Live\_API\_OFF/Live\_API\_ON] allows System 2 to respond (when set to ON) to transport controls as received from the remote computer (System 2) but will ignore tempo changes;
- The second toggle [Sync\_OFF/Syn\_ON] performs the same in terms of transport actions but with additional tempo synchronization (if set on set's the other toggle also automatically to on).

We choose in this case the bottom toggle and set it to "Sync\_ON".



From now on the two Live sets are synchronized also in tempo and transport.